Slivisu User Manual

Table of Contents

Topic	Page
<u>Description</u>	3
Supported Data Format	4
Connecting to Database	10
1. Exploration of Observation Data	12
1.1 SLI-Hierarchy	13
1.2 RSL Categories	15
1.3 SLI Table	23
1.4 Sea Level Curve	26
1.5 SLI Time Histogram	35
1.6 Time Scale	41
<u>1.7 Map</u>	43
2. Exploration of Model Data	52
2.1 Scatterplot Matrix	54
2.2 3D Scatterplot	56
2.3 Scatterplot	58
2.4 Model Histogram	61
2.5 Model Table	65
2.6 Fit Scale	67
3. Brushing and Linking	71

Slivisu - A visual analytics tool to validate simulation models against collected data

To support the scientists in gaining insight into the data and the consistency between data and model, Slivisu was developed to fulfil the following tasks:

Making apparent

- the distribution of collected data over over space and time
- the various quality measures of the collected data
- the difference of calculated and modelled data in space and time

A combination of methods from analysis and visualization is applied in the concept to support the tasks:

- The Sea Level Indicator (SLI) data are clustered according to the collection process or data availability; the cluster is presented by an adaptive convex bounding box.
- All information about the SLIs in a cluster is summarized in a multivariate summation diagram which depicts the number of SLIs of a certain quality in various time intervals
- Information about single SLIs can be presented interactively on demand

Supported Data Format

PostgreSQL DB

• Example:

Host: adsc.gfz-potsdam.de

Database: RSL2 Port: 5432 Scheme: rsl

Attribute Table: slivisu_attribs

with the respective username and password given.

Observation Data

For full functionality create a table *rsl.slivisu_attribs* which connects the native column names to those expected in slivisu. There, the information can be placed for different tables inside the database.

Attribute Type		Description
relation	varchar(16)	Name of relation
rel_id	varchar(16)	Name of id
tab_name	varchar(16)	Name of region
curve	varchar(16)	Name of sea level curve
lat	varchar(16)	Latitude
long	varchar(16)	Longitude
rsl_min	varchar(16)	minimum of rsl
rsl_max	varchar(16)	maximum of rsl
cal_min	varchar(16)	Calibrated minimum age
cal_max	varchar(16)	Calibrated maximum age

Observation Data

The following attributes are optional. If the attribute does not exist, or the entry is empty, they are calculated from the respective equation below in the program.

cal_age	varchar(16)	Mean calibrated age, may differ from (cal_min+cal_max)/2
cal_std	varchar(16)	Standard error of age, may differ from (cal_max-cal_min)/2
rsl_mean	varchar(16)	Mean derived sea-level height, may differ from (rsl_min + rsl_max)/2
rsl_err	varchar(16)	Standard error of height determination, may differ from (rsl_max-rsl_min)/2
gid_gen	varchar(32)	contains format of global id for SLIs. E.g. gid = 'DYKE-%5.5i' rel_id

Model Data

- External data ahead of the database can be read in.
- SLIVISU/selection/blub.sel or SLIVISU/data/blub.lis
- Selection, .sel
 - Selections, that can be loaded or saved are newline separated lists of gid's in files ending with sel. These will be marked in the views, if the respective SLIs exist in the Listing. If not, the loaded selection is reduced to those gid's. But keep in mind, that with improper ending the file content is ignored.
- Parameter listing, .lis
 - A parameter listing is provided in .lis files, which contain for a set of models the parameter values and filenames where RSL predictions and calculated fits or deviations at the respective SLIs are given.

Model Data

.sel Files:

• newline separated lists of gid's in files ending with sel



Model Data


.lis Files:

- num is the number of parameters or dimension of the parameter space.
- name# gives the annotated name in the respective view,
- min# and range# gives the minimum value and range of the respective parameter for the representations in 'cube' and the other parameter charts and matrix.
- In the following data list, the first column gives the filename which is considered relative to the directory where the .lis is located and the following columns, 2, ..., num+1, give the considered par for each model.
- The parameter name and arrays are due to the name space used in this program, as the type definition follows after # at the beginning of each line. s is string, d and f is for double and single float.


```
ignormal out.lis
      #s num = 3
      #s name1 = Thickness lithosphere // name of parameter
      #s name2 = log (viscosity UM) // name of parameter
      #s name3 = log (viscosity LM) // name of parameter
      #d min1 = 70 // minimum in scale
      #d min2 = 20
      #d min3 = 21
     #d range1 = 60 // range in scale
      #d range2 = 1
 10
     #d range3 = 2
     #sfff [visc list] dirname - par1 - par2 - par3 // name and parameters
     L100 -vm2/SLI data f.out 110 20.6021 21.301
     L100 1010/SLI data f.out 100 20.301 21.699
     L100 1020/SLI data f.out 100 20.6021 21.699
     L100 1030/SLI data f.out 100 20.7782 21.699
     L100 1040/SLI data f.out 100 20.9031 21.699
     L100 2010/SLI data f.out 100 20.301 22
     L100 2020/SLI data f.out 100 20.6021 22
     L100 2025/SLI data f.out 80 20.699 22
     L100 2030/SLI data f.out 100 20.7782 22
     L100 2040/SLI data f.out 100 20.9031 22
```

Connecting to Database

- Observation Data DB:
- Choose parameters on start
- When using a different database, the login of course
 has to be modified, but in the respective theme a table
 like slivisu_attribs has to exist, which relates the
 attribute names of the respective table containing the
 data to the column which is interpreted in SLIVISU.
- Click on *Test Connection*, green = connection established, yellow = connecting, red = connection failed
- Save & Connect to start




1. Exploration of Observation data



SLI Hierarchy:


The hierarchy describes a regional definement inside a table


- Database (complete SLI Database)
- SQL-Table (in this case: ant)
 - Table (tab_name, in this case: Antarctic Pen)
 - Subregion (curve, in this case: South Shetland Islands)
 - Single SLI (ant_-00538)




[0/4/581] = 0 SLIs marked, 4 selected, 581 total


- Select a subset of SLIs by selecting hierarchy levels or single SLIs:
- Selecting a checkbox automatically selects every SLI on sublevels
 to unfold sublevels click on the circle next to the checkbox






- The four default categories upper, lower, band and none are automatically selected on start
- upper: SLIs with given rsl_max and empty rsl_min
- lower: SLIs with empty rsl_max and given rsl_min
- band: SLIs with given rsl_max and given rsl_min
- none: SLIs with empty rsl_max and empty rsl_min
- to edit a category or define new categories click on Edit





Spe <u>i</u> chern in	: 🗂 filter	▼ あ 🛨 🖈
spe <u>i</u> chern in	. Inter	
image		
== sql		
default.c	esv	
<u>D</u> ateiname:	myCategories	
	myCategories CSV-File (*.csv)	
<u>O</u> ateiname: Da <u>t</u> eityp:		Speichern Abbrechen


Save your category file in SLIVISU/filter




Load your category file and select your category




- should be located in SLIVISU/filter/mycsv.csv
- the querys are stored seperately in SLIVISU/filter/sql
- they can be edited in any text editor too
- Example default.csv:






- SLI color depends on it's category. The priority is from left to right, you might need to deselect the default categories or reorder them to see your category in the other views
- To do so click on Order




- Click and hold a Category and move it to it's new place
- Click *ok* when done







gid	tab name	curve	default cate		lat	long	cal_min	cal_max	cal_sig	min_rsl	max_rsl	dyke_id	loc
YKE-04594	Hudson	Ungava Bay W, QC	lower		61,033	-69,925	7310	7695	1	66	1110/_101		Koartac
YKE-04595	Hudson	Ungava Bay W, QC	lower		60,083	-70,383	7260	7560	1	52		-	Payne R
YKE-04597	Hudson	Akpatok Island, NU	band		60,573	-68,168	8690	9190	1	76	100		north coast
VKE-04598	Hudson	Akpatok Island, NU	band		60,442	-68,317	6735	8650	1	82	91		west coast
YKE-04599	Hudson	Akpatok Island, NU	none		60,5	-67,85	13650	14300	1			4599	
VKE-04600	Hudson	Akpatok Island, NU	band		60,5	-67,85	8975	9380	1	69	80	4600	NE
VKE-04601	Hudson	Akpatok Island, NU	band		60,5	-67,85	8385	8570	1	76	81	4601	
YKE-04602	Hudson	Akpatok Island, NU	none		60,583	-68,2	9450	9675	1	0	0	4602	into et processor la
VKE-04603	Hudson	Akpatok Island, NU	band		60,5	-67,85	7860	8240	1	76	90	4603	
YKE-04604	Hudson	Akpatok Island, NU	lower		60,5	-67,85	7555	7855	1	42		4604	Ī
YKE-04605	Hudson	Akpatok Island, NU	lower		60,5	-67,85	7510	7765	1	13		4605	
YKE-04606	Hudson	Akpatok Island, NU	lower		60,5	-67,85	7200	7565	1	58		4606	
YKE-04607	Hudson	Akpatok Island, NU	lower		60,5	-67,85	6450	6870	1	33		4607	
OYKE-04608	Hudson	Akpatok Island, NU	lower		60,45	-68,317	810	1155	1	7		4608	
YKE-04610	Hudson	Diana Island, QC/NU	upper		60,936	-69,976	1225	1510	1		8	4610	longhouse
YKE-04611	Hudson	Diana Island, QC/NU	upper		60,709	-69,624	910	1210	1		8,4	4611	UNG.11-A
THE STATE		p. 11 . 004	4		00.700	00.004	1055	1-1-	- 1			4040	
			4	WHERE				15.00.000	(E)	V2	25.00		

- SLI Table contains all the information from the database for the selected SLIs plus their categories
- yellow columns are marked SLIs




- sort the table by clicking on a column header
- to select or deselect SLIs in the SLI-Table click on their row (ctrl + click for adding SLIs to the selection)
- or write a SQL-Query in the field and click on *Start Query*, this will automatically mark all fitting SLIs in the open table
- Invert Selection inverts the selection
- Right Click opens the pop-up menu:
 - Show only Selected hides non selected SLIs in the **SLI-Table**
 - Invert Selection inverts the selection
 - Reduce to Selection does not work on more than one table! Other tables will be closed.






- Sea Level Curve for individual samples
- X: uncertainty interval of time point
- Y: uncertainty interval of value (height)
- Color: interval type / category




- Select by clicking and drawing a rectangle over the shapes
- Marked samples are yellow
- right click on the slider opens the edit menu where max height and min height can be adjusted
- adjust the scale on the right to view only SLIs within the selected height range by moving the sliders



Right click opens the pop-up menu




When Only selection is checked, only the marked SLIs are shown





When *SLI-category differentiation* is unchecked, only the marked SLIs are shown in their category color, other SLIs appear dark grey.








Shape types changes the form of the SLIs, default is *line object 1*













- When show model(s) is checked, the model points are shown with their Goodness of Fit color
- show average fit shows them in the color of the average model fit
- Export to LIS-File: save the selected SLIs in lis-Format


Lis Format for Sea Level Curve:

```
SLC.lis
     #s visual query = SeaLevelCurve
     #s [sli tables] table
     dyke
                                                                                                           L100 1010 height - fit L100 1030 - L100 1030 height
    #sdddddd [slis from SLC] SLIcode - time min - time max - hsli min - hsli max - category
                                                                                            fit L100 1010
                                        50.0
                                                       1.0 41.821 1.0 34.747
    DYKE-00664 8380
                        9035
                                26.0
                                               band
                                                                            1.0 -7.1531 1.0 -5.4194
    DYKE-00013 2850
                        3935
                                1.89999997615814
                                                   1.89999997615814
                                                                      upper
                                                                  upper 1.0 -1.7385 1.0 -1.4669
     DYKE-00018 785 1270
                            2.16000008583069
                                               2.16000008583069
                                                                                                               model fit and height
                           2.0 2.0 upper 1.0 -1.0546 1.0 -0.57788
     DYKE-00109 915 1300
                                                                      upper 1.0 -8.355 1.0 -6.145 (only if at least one model is selected)
                                3.90000009536743
                                                   3.90000009536743
     DYKE-00032 3130
                        4620
                               2.0 2.0 upper
                                               1.0 -1.5755 1.0 -0.8791
     DYKE-00114 1305
                        1825
                                                      1.0 64.793 1.0 71.268
     DYKE-01546 6165
                        6660
                                64.0
                                       83.0
                                               band
     DYKE-00737 7560
                        7865
                                20.0
                                       25.0
                                               band
                                                      1.0 25.877 0.0 12.809
    DYKE-00094 645 800 4.0 4.0 upper
                                      1.0 -0.62295
                                                       1.0 -0.34063
                                4.5 4.5 upper
                                               1.0 -109.85 1.0 -89.548
                        18175
     DYKE-00009 15405
                              -19.0 -19.0
     DYKE-00061 11070
                        12965
                                               upper 1.0 -52.404 1.0 -52.133
                                4.0 4.0 upper 1.0 -2.6626 1.0 -1.565
     DYKE-00084 2360
                        2745
```







- Number of samples in a time interval grouped by type
- X: Time, Y: number
- yellow overlayed parts show the number of marked samples in the category/time interval





- A tooltip shows details about the category and the time interval by hovering the mouse over
- Selection of bins with click or ctrl + click



Right click opens the pop-up menu












• Check *Marked SLI in seperate* bar to see the number of marked samples inside a time interval in a seperate bar








SLI Time Histogram




- Unchecking SLI-category differentiation shows total count only
- Unchecking *Show total count* bar removes the grey seperate bar (in combination with *marked SLI in seperate bar*)
- Export to LIS-File: save the selected SLIs


Lis Format for **SLI Time Histogram**:

```
Histo.lis 🚨
     #s visual query = TimeHistogram
     #s [sli tables] table
     dyke
     #sdd [slis from histogram] SLIcode - bar time min - bar time max - category
    DYKE-07363 -5.0
                        2371.0 upper
     DYKE-05305 2371.0 4748.0 upper
     DYKE-08990 4748.0 7124.0 lower
     DYKE-08607 11877.0 14254.0 band
     DYKE-06598 2371.0 4748.0 upper
 10
     DYKE-02665 9501.0 11877.0 band
 11
     DYKE-06028 2371.0 4748.0 upper
     DYKE-08524 11877.0 14254.0 none
     DYKE-03932 7124.0 9501.0 lower
 13
 14
     DYKE-00433 9501.0 11877.0 upper
```












Spatial distribution of samples and sample groups




- The name of a SLI or curve is shown at the top by hovering over it with the mouse
- "Grab" the map with the left mouse button to pan it
- Zooming is possible with the mouse wheel






- select a (sub)region by clicking in the polygon
- or select single SLIs by clicking (ctrl + click adds SLI to selection)



- After reading in model data, the layers for regions will have the average fit color (see Fitscale)
- SLI points keep their category color
- to see their goodness of fit color select *Model Fits* from the pop-up menu (right click)
- on selection of indicators in **SLI Table**, the fit is not adjusted here, but depends on the SLIs existing in the table




- Check Selection only to see only marked SLIs
- Chose Export to LIS-File to save the selected SLIs


Lis Format for Map:

```
Map.lis
     #s visual query = Map
                                                                               model fit
     #s [sli tables] table
                                                                   (only if at least one model is selected)
     dyke
     #sdddd [slis for map] SLIcode - lat - lon - tab name:curve - fit L100 1010 - fit L100 1030
     DYKE-00664 66.1417007446289
                                     -65.7249984741211
                                                         Baffin E: Pangnirtung F, Baffin I, NU
                                                                                                 1.0 1.0
     DYKE-00013 71.3167037963867
                                     -156.567001342773
                                                         Alaska N:Pt Barrow, AK 1.0 1.0
     DYKE-00018 71.38330078125 -156.483001708984
                                                     Alaska N:Pt Barrow, AK 1.0 1.0
     DYKE-00109 67.1667022705078
                                     -163.5 Alaska N: Kotzebue Sound, AK 1.0 1.0
     DYKE-00032 71.25 -156.75 Alaska N:Pt Barrow, AK 1.0 1.0
     DYKE-00114 67.1667022705078
                                     -163.5 Alaska N: Kotzebue Sound, AK 1.0 1.0
 10
```

- Click on Layer in the lower left corner to open the layers menu
- *tab*: Polygons for the tables (SQL-Table)
- tab_name: Polygons for the regions (tab_name)
- curve: Polygons for the subregions (curve)
- flags: show goodness of fit histogram
- SLIs: SLI points









Time from past to present




- color = goodness of fit
- length = number of SLIs in time interval


2. Exploration of Model Data









- A Scatterplot Matrix for the model parameters
- Moving the mouse over an instance shows details as tool tip






3D Scatterplot


- Axes: model parameters
- Cubes: model instances
- Cube color: aggregated goodness of fit
- Turn the cube with the keyboard as shown in the graphic above (or with the mouse, X-Axis only)
- Reset brings the cube back in the default position







Scatterplot

- The selected plot from the Scatterplot Matrix in detail
- Moving the mouse over an instance shows details as tool tip










Model Histogram

- One histogram for each model parameter
- X: parameter value
- Y: stack of model instances sorted by goodness of fit




- Moving the mouse over an instance shows details as tool tip
- Select a model instance by clicking on the square
 A yellow frame shows which instance is selected
- Ctrl + click to add further models
- Unselect by clicking outside an existing model






	Model Histograms Model Tab	//.		0.23	S. 100 S. 20 S		to an about	81
model	Thickness lithosphere *	log (viscosity UM)	log (viscosity LM)	fit	fuzzyfit0	fuzzyfit1	fuzzyfit2	
_100_1010	100	20,301	21,699	1	8,0	1,01	0,71	3
.100_1020	100	20,602	21,699	1	0,787	1,055	0,725	
.100_1030	100	20,778	21,699	1	0,868	0,805	0,635	
.100_1040	100	20,903	21,699	1	0,908	0,705	0,595	
100_2010	100	20,301	22	1	0,668	1,585	0,89	
.100_2020	100	20,602	22	1	0,759	1,155	0,76	
100_2030	100	20,778	22	1	0,909	0,7	0,59	
100_2040	100	20,903	22	1	0,989	0,52	0,51	
100_3010	100	20,301	22,301	1	0,643	1,75	0,935	
100_3020	100	20,602	22,301	1	0,838	0,89	0,665	
100_3030	100	20,778	22,301	1	1	0	0	
100_3040	100	20,903	22,301	1	1	0	0	
100_4010	100	20,301	22,602	1	0,657	1,655	0,91	
100_4020	☑ Fit Filter (enabled)	20,602	22,602	1	0,93	0,65	0,57	
100_4030	selection mode	20,778	22,602	1	1	0	0,001	
100_4040	fit column) fit)3	22,602	1	1	0	0,001	
100_2025	TIL COMMITT	99	22	1	0,858	0,83	0,645	
80_1010	80	fuzzyfit0 01	21,699	1	0,819	0,95	0,69	
80_1020	80	fuzzyfit1 02	21,699	1	0,811	0,975	0,7	
80_1030	80	☑ fuzzyfit2 78	21,699	1	0,882	0,77	0,62	
80_1040	80	20,903	21,699	1	0,912	0,69	0,59	
80_2010	80	20,301	22	1	0,69	1,465	0,855	
80_2020	80	20,602	22	1	0,781	1,075	0,735	
80_2025	80	20,699	22	1	0,858	0,83	0,645	
80 2030	80	20,778	22	1	0,917	0.68	0,585	

- Model table containing all the information from the model data file plus the model fits
- yellow rows are marked model instances
- In the model column, the color shows the average model fit for the selected SLIs
- sort the table by clicking on a column header
- right click opens the pop up menu where the fit column can be chosen





The **Fit Scale** shows

- which norm is used to calculate the goodness of fit
- the color scale for the goodness of fit
- click on edit to open the settings menu
 - min/max: scale range, default it 0 to 1.2
 - Colorscheme: colors for the goodness of it, default is red
 - segments: number of different colors, default is 6
 - norm: Fuzzy: 1- norm, Euclid: 2 -norm, p-Norm:

$$\mathit{fit} = (1/N\sum_{i=1}^{N}\mathit{fit}_{i}^{p})^{1/p}$$

